## 1. 串口配置

```
Baudrate: 115200
 Data Bits: 8
 Parity:
         none
 Stop Bits: 1
2. PC发送字符串命令以\n或者\r结束,控制板返回命令以 \r\n>>结束
3. 命令列表可以发送help查看;命令格式: cmd 参数1 参数2 ...
4. 连续发送多条命令时间间隔需大于10ms
 通讯受干扰返回command not found的话,请重发命令。
        命令列表打印
help
        打印板卡信息
version
        控制卡重启
reboot
基本命令:
readinput <ch> 读取输入通道ch的状态
        readinput 1
                         send2:
                                    readinput 1 2 2 3
send1:
receive1: in[1]=0
                                   in[1]=0,in[2]=0,in[2]=0,in[3]=0
                         receive2:
output on <ch> 设置输出通道ch状态为1
send1:
                         send2:
                                   output on 1 2 2 3
        output on 1
                                   out[1]=1,out[2]=1,out[2]=1,out[3]=1
receive1: out[1]=1
                         receive2:
output off <ch> 设置输出通道ch状态为0
send1:
        output off 1
                                   output off 1 2 2 3
                         send2:
receive1: out[1]=0
                         receive2: out[1]=0,out[2]=0,out[2]=0,out[3]=0
savedata <page> <data> 在1~200存储位置写入数据
              (最大长度为64个字符,不支持数据带空格,需要把空格用其他字符替换)
       savedata 1 this_data_is_for_test:position1=100;position2=200;
send:
receive: savedata[1] ok
readdata <page> 读取1~200存储位置数据
send:
       readdata 1
receive: readdata[1]=this_data_is_for_test:position1=100;position2=200;
电机相关命令(axis_number=0~2; speed=1~2047, 不需要设置加速度, 内部自动处理)
  ---后续使用的双层板卡+电机模块+外置驱动器(1600脉冲一圈)
   速度105代表0.25RPS (revolutions per second), 其他速度按比例计算
motor gohome <axis_number> <speed> 电机以设定的速度开始回原点
send:
        motor gohome 1 -200
       电机先左转找到左限位后再右转,触发原点传感器后,设置当前位置为原点
receive: motor[1] is start go home by searching home sensor
motor golimit <axis_number> <speed> 电机以设定的速度开始回限位点
send:
        motor golimit 1 200
      电机右转找到限位后停止, 并设置当前位置为原点
receive: motor[1] is start go home by searching limit sensor
motor stop <axis_number> 电机停止运行并返回当前位置
send:
        motor stop 1
receive: motor[1] is stop and P[1]=0
motor set speed <axis_number> <value> 设定电机运行速度
send:
        motor set speed 1 105
receive: set motor[1] speed=105 ok
motor move <axis_number> <position> 电机相对运动设定值
     motor move 1 1000
receive: motor[1] is start to make relative motion
motor moveto <axis_number> <position> 电机相绝对运动到设定的位置
        motor moveto 1 1000
send:
receive: motor[1] is start to make absolute motion
motor get position <axis_number> 读取对应轴当前位置
        motor get position 1
send:
receive: motor[1] actual position=0
motor get leftLimit <axis_number>
                              读取对应轴左限位状态
motor get rightLimit <axis number> 读取对应轴右限位状态
        motor get leftLimit 1
send:
receive: motor[1] left switch status=0
motor get is_homed <axis_number> 读取对应轴回原点是否0K
```

motor get is\_homed 1

send:

receive: motor[1] homed=1

motor get is\_stop <axis\_number> 读取对应轴回原点是否0K

send: motor get is\_stop 1
receive: motor[1] stop=1

motor set limitSignal <axis\_number> <value> 更改设置限位触发的电平为1或者0

## 项目应用命令

## printdata

send: printdata

receive: P[1]=3628,Press=+000.005@ P[1]=3628,Press=+000.005@

motor[1] is stop and stop printing data